
Notifications

Settings → notifications chooses the automatic messages sent to subscribers and the messages shown to managers. Extra fields appear when you turn a switch on.



User Notifications

Field	Description
Email Notifications	Sends emails to subscribers on activation, registration, expiration warning and termination. Choose a template for each (below).
User Activation Template	Email sent after the service is activated.
User Registration Template	Email sent when a user is created.

Field	Description
User Expiration Warning Template	Email sent before the subscription expires.
User Termination Template	Email sent when the subscription ends.
Notify via SMS on activation	Sends the *Activation SMS* (text set on the SMS page) after activation.
Notify via SMS on expiration	Sends the *SMS before expiration* a few days before the subscription expires.
Send SMS before expiration in	1–4 days before expiration (default 3).
Notify via Email on expiration	Sends the expiration warning email a few days before expiration. Works even if *Email Notifications* is OFF, as long as a template is chosen.
Send email before expiration in	1–4 days before expiration (default 3).

Email texts are written in Email Templates. SMS need **Enable SMS Service** ON on the SMS page and a phone number on the user. Emails need a working Email Settings configuration and an email address on the user.

Manager Notifications

Field	Description
Show dashboard notification	Shows a fixed banner on every manager's dashboard, for example news or a maintenance notice.
Dashboard notification type	Colour of the banner: Info, Green, Yellow or Red alert.
Dashboard Notification Text	The banner text.
Show Login Page Message	Shows a message on the admin panel login page.
Manager Login Page Message	The login page message text.
Show Welcome Screen On Login	Shows an announcement window to managers when they open the dashboard. Click **Screen Editor** to write it. See Welcome Screen.

User FUP Notification

Sent when a subscriber reaches the fair usage limit and is moved to the reduced (FUP) profile.

Field	Description

Notify via SMS / SMS Text	Sends an SMS with this text.
Notify via Email / Email Template	Sends an email with the chosen template.
Show Notification on FUP / text	Shows this message to the subscriber (not an SMS). The text field below the switch is also labelled "SMS Text".

Required permission: Settings - System Settings

Revision #7
Created 2023-06-14 07:56:10 UTC by Admin
Updated 2026-11-07 20:28:48 UTC by Admin